

WorldCard Team - Windows Server Edition

Administrator Manual

Version: v1.5

Release: June, 2019

WorldCard Team License Agreement

This is an agreement between you and PENPOWER TECHNOLOGY LTD. (“PenPower”) for the software product of WorldCard Team (the “Software”) accompanying this Software License Agreement (“Agreement”).

The Software includes the software for Server / iOS / Android / Windows / Mac / Web. Before installation or use of the Software, you must read and accept the terms and conditions of this Agreement as follows. By using or installing the Software you represent that you have carefully read and expressly accept all terms and conditions contained in this Agreement and will be legally bound by the terms and conditions hereunder.

If you do not accept the terms and conditions of this Agreement, please do not install or use the Software.

1. Grant of License.

PenPower grants you a nonexclusive license to use the Software and its functionalities solely for your internal business purpose and that your use of the Software must comply with the terms and conditions of this Agreement. The Software is only licensed and not sold to you by PenPower.

2. Installation and Use

You may install and use the Software only for the number of licenses acquired by you. In order to exercise your rights to the Software under this Agreement, you must activate your copy of the Software in the manner described during the launch sequence.

3. Ownership

PenPower retains all right and related interest in and to the Software and all copies at all times, regardless of the form or media in or on which the original or other copies may subsequently exist. You neither own nor hereby acquire any claim or right of ownership to the Software or to any related patents, copyrights, trademarks or other intellectual property rights.

4. Copyright

The Software is copyrighted by PenPower and is protected by copyright and patent laws of Republic of China (ROC) and international treaty provisions. You shall not copy the Software except to install the Software components licensed by you, as set forth by law, on to computers as part of executing the Software.

5. Restrictions

Except as expressly permitted by this Agreement or by applicable law you shall not: (a) lease, loan, resell, assign, sublicense, or otherwise distribute the Software or any of the rights granted by this Agreement; (b) modify (even for purpose of error correction), or translate the Software or create derivative works therefrom except as necessary to configure the Software using the menus, options and tools contained in the Software; (c) in any way reverse engineer, disassemble or decompile (including reverse compiling to ensure interoperability) the Software or any portion thereof; (d) use unauthorized keycode(s) or distribute keycode(s); (e) permit third party access to,

or use of the Software, and (f) distribute or publish keycode(s).

6. Limited Warranty and Remedy

(a) PenPower warrants that the Software will conform to the functional description set forth in its standard documentation, but does not warrant that the use of the Software will operate uninterrupted or error free. Any revisions or upgrades to the Software shall not restart or affect the warranty period.

(b) You agree that your remedy for breach of the above-stated limited warranty shall be, either: (i) correction or replacement of the Software with products which conform to the above-stated limited warranty; or (ii) return of the price paid for the Software and termination of this Agreement. Such remedy shall be provided to you by PenPower only if you give PenPower written notice of any breach of the above-stated limited warranty, within thirty (30) days of receipt of the Software.

(C) EXCEPT FOR EXPRESS WARRANTIES STATED IN THIS SECTION 6, PENPOWER DISCLAIMS ALL OTHER WARRANTIES, INCLUDING WITHOUT LIMITATION, (I) OF MERCHANTABILITY, (II) OF FITNESS FOR A PARTICULAR PURPOSE, (III) OF NON-INFRINGEMENT OF THIRD PARTY RIGHTS, OR (IV) AGAINST HIDDEN DEFECTS. YOU ACKNOWLEDGE THAT IN ENTERING INTO THIS AGREEMENT, YOU HAVE RELIED UPON YOUR OWN EXPERIENCE, SKILL AND JUDGEMENT TO EVALUATE THE SOFTWARE AND TO ENSURE THAT THE SOFTWARE MEETS YOUR REQUIREMENTS.

7. Third Party Offerings

The Software may allow you to access the contents, software applications and data services of a third party, including but not limited to a variety of Internet applications ("Third Party Offerings") and interoperate with them. Your access to and use of any Third Party Offering is governed by the agreed terms and conditions in connection with the offering and the copyright laws of the country the third party belongs to.

Third Party Offerings are not owned or provided by the PenPower. Third Party Offerings may at any time for any reason be modified or discontinued. PenPower does not control, endorse, or accept any responsibility associated with Third Party Offerings. Any agreement between you and any third party in connection with a Third Party Offering, including privacy policies and use of your personal information, delivery of and payment for goods and services, and any other terms, conditions, warranties, or representations of the third party associated with such agreement is solely a dealing between you and the third party. You should take into consideration and shall assume all risks or responsibilities in connection with the use of "Third Party Offerings."

8. Privacy Policy

This privacy policy explains what information PenPower may collect about you, how PenPower and other companies may use it, and tracking technologies that may be used

to collect information. When you use our sites or our mobile applications (our "apps"), PenPower collect information about you and use it to facilitate and improve our services. PenPower may change this Privacy Policy at any time by posting a revised Privacy Policy on this page or apps download screen and such changes will be effective upon posting.

Information PenPower collect

a. Information collected automatically: When you visit our sites and use our apps, PenPower automatically collect and store information about your computer or mobile device and your activities. This information may include:

Your computer's or mobile device's IP address

Technical information about your computer or mobile device (such as type of device, web browser or operating system)

Your preferences and settings (time zone, language, etc.)

Your computer's or mobile device's unique ID number

Your mobile device's geographic location (specific geographic location if you've enabled collection of that information, or general geographic location automatically)

How long you visited our sites or used our apps and which services and features you used

b. Information you choose to provide: You may choose to open an account and provide us with information in order to use certain services or to take advantage of special offers. This information may include your name, serial number and related information of the services, email address, phone number. You may choose not to provide us with any personally identifiable information. But if you don't provide certain information, you won't be able to use some of the services PenPower offer.

How PenPower use your information

We use your information to provide and improve our services, customize services for you, make special offers, better understand our users, diagnose and fix problems, and sell and display ads that may be relevant to you.

Email Address: PenPower use your email address only to allow you to log in to your account, send you confirmations (of your registration, purchase, etc.), and to send you messages as part of our services. PenPower will also use your email address to respond to your customer service inquiries.

Phone Number: PenPower use your mobile phone number only to send you SMS messages that you've requested.

Advertisers : Advertisers and advertising networks use tracking technologies to collect information about users' computers or mobile devices and their online activities (for example, web pages visited and searches made) as well as general geographic location and use that information to display targeted ads to users. PenPower sometimes allow these ad

companies to collect such information when you use our sites and apps to enable them to display targeted ads to you.

Legal Matters: PenPower may use or disclose user information: in response to a legal request, such as a subpoena, court order, or government demand; to comply with the law; in connection with a threat of litigation; to investigate or report illegal activity; to protect the legal rights of PENPOWER, our customers, our sites and apps or users of our sites and apps; or to enforce our rights or defend claims. PenPower may also transfer your information to another company in connection with a corporate restructuring, such as a sale or merger.

Mobile Device IDs: If you're using an app, PenPower use mobile device IDs (the unique identifier assigned to a device by the manufacturer), instead of cookies, to recognize you.

Apps

If you install one of our apps on your mobile device, your use of the app is subject to our app license agreement.

9. Limitation of Liability

To the extent permitted by applicable law or this Agreement, in no event PenPower shall be liable to you or any third party for any direct or indirect damages or costs, including without limitation, any lost profits or revenues, loss or inaccuracy of data, or cost of substitute goods, regardless of the theory of liability (including negligence) and even if PenPower has been advised of the possibility of such damages.

In any event, PenPower's total aggregate liability to you for actual direct damages for using the Software shall be limited to the Software license fees paid by you for the Software.

10. Termination

This Agreement is effective until terminated. You may terminate this Agreement at any time by providing PenPower with written notice. Except as otherwise specified in this Agreement, you will not receive any refund of fees.

This Agreement may be terminated by PenPower in the event that: (i) you fail to pay the license fees and other charges set forth at the time of your order; or (ii) you fail to comply with any of the terms and conditions set forth in this Agreement and do not rectify such failure within thirty (30) days after receiving notice thereof. Termination shall not relieve you from your obligation to pay fees that remain unpaid. Upon termination by PenPower of this Agreement, PenPower shall have no obligation to refund to you any fees paid by you.

Upon any termination of this Agreement, you shall: (i) immediately cease all use of the Software, including the use and distribution of any custom applications incorporating the Software; and (ii) return the Software to PenPower or destroy same, and certify to PenPower, in writing, that all copies and partial copies thereof have been returned or completely destroyed and are no longer being used.

11. General

If any provision of this Agreement is ruled invalid, such invalidity shall not affect the validity of the remaining portions of this Agreement. This Agreement constitutes the entire agreement between you and PenPower, and supersedes any prior agreement, whether written or oral, relating to the subject matter of this Agreement.

12. Governing Law

This Agreement is governed by the laws of Republic of China (ROC).

Menu

Chapter 1 Server Build Requirements.....	1 - 1
1.1 Hardware Specifications.....	1 - 1
1.2 Operating System	1 - 1
1.3 Database Software	1 - 1
1.4 Essential Environment Kits	1 - 2
1.4.1 Install Essential Environment Kits	1 - 3
Chapter 2 Database Settings (MSSQL or Postgre)	2 - 1
2.1 Microsoft SQL Server Related Settings.....	2 - 1
2.1.1 Add Microsoft SQL Server Database Account for WorldCard Team.....	2 - 1
2.1.2 Confirm Microsoft SQL Server Database connection Parameters.....	2 - 3
2.2 PostgreSQL Distributed Architecture Service Settings	2 - 4
Chapter 3 Connect Database via WorldCard Team Startup Tool.....	3 - 1
3.1 Quick Startup Settings	3 - 1
3.2 Advanced Startup Settings.....	3 - 4
Microsoft SQL Server	3 - 5
PostgreSQL.....	3 - 5
Chapter 4 Activate WorldCard Team Service.....	4 - 1
4.1 Register WorldCard Team.....	4 - 1
4.2 Create User Accounts	4 - 1
4.3 Start to Use	4 - 3
4.4 Firewall Settings	4 - 4
4.5 External Connection Settings	4 - 6
Chapter 5 WorldCard Team Settings.....	5 - 1
5.1 Basic Operations.....	5 - 1
5.1.1 Change Password / Display Name	5 - 1
5.1.2 Switch Interface Language.....	5 - 1
5.1.3 Back to Homepage / Sign Out.....	5 - 1
5.2 Admin Settings	5 - 1
5.2.1 Manage Accounts	5 - 1
5.2.2 Delete/Deactivate/Suspend User Account.....	5 - 3
5.2.3 Import Account from AD Server	5 - 4

5.2.4 Sharing Rules	5-5
5.2.5 CRM Settings	5-5
5.2.6 Custom Field	5-5
5.2.7 System Overview	5-6
5.2.8 Certificate Information	5-6
5.2.9 Security Settings.....	5-6
5.3 General Settings.....	5-7
5.3.1 Share Settings.....	5-7
5.3.2 Display Settings.....	5-7
5.3.3 CRM Settings	5-8
5.4 Notification.....	5-8
Chapter 6 WorldCard Team Applications Installation	6-1
Chapter 7 Database Backup / Restore	7-1
7.1 Back up Microsoft SQL Server Database.....	7-1
7.2 Restore Microsoft SQL Server Database.....	7-2
7.3 Back up PostgreSQL Database	7-4
7.4 Restore PostgreSQL Database	7-6
Appendix A: Connecting Information of AD Server	A-1
Appendix B: AN240W Duplex Scanner Instructions (Optional).....	B-1
B.1 Hardware Function Introduction.....	B-1
B.2 Installation and Setup.....	B-2
B.3 Start Scanning Business Cards.....	B-3

There may be newer versions of the software that was released during or after this product's manufacturing date. If the content in the User Manual differs from the on-screen interface, please follow the instructions on the on-screen interface instead of the User Manual.

History

v1.5.0

- Add [URL] field option of User Defined Field function.

Page 5-6

v1.4.0

- Add user suspension mechanism.

v1.3.0

- Add WorldCard Team Startup tool.
- Add platform restrictions and device binding function.
- Add IP connection restriction.
- Add notification function after database restore.

v1.2.1

- Add JRE download instructions.
- Revise JRE set up instructions.

v1.2.0

- Year 2017, first version.

Chapter 1 Server Build Requirements

1.1 Hardware Specifications

The following is the minimum required hardware specifications:

- Processor: 1.6GHz Quad-Core processor.
- Memory: 8GB.
- Hard Disk: 1TB capacity. It is recommended to build up RAID 1 type to protect data.

1.2 Operating System

Choose one of the following supported versions of operating system to use:

- Microsoft Windows Server 2012 (64 bit).
- Microsoft Windows Server 2012 R2 (64 bit), or later.
- Microsoft Windows 7 Service Pack 1 (64 bit), or later.

1.3 Database Software

Choose one of the following supported database software to use:

- Microsoft SQL Server 2012 (32/64 bit).
- Microsoft SQL Server 2014 (32/64 bit).
- Microsoft SQL Server 2016 (64 bit).
- Microsoft SQL Server 2017 (64 bit).
- PostgreSQL 9.2, 9.3, 9.4, 9.5, 9.6, 10.

Note: Microsoft SQL Server Express version is not supported.

Reminder: It is recommended to use PostgreSQL version 9.6 and tick to install pgAdmin tool, but no need to install Stack Builder package.



1.4 Essential Environment Kits

Please install the following essential environment kits:

- Java SE Runtime Environment 8 (JRE)
- Microsoft .NET Framework 4.5 or later.

How to download the JRE kit (The following is for reference only, please refer to the actual situation.)

Please access the following URL:

(<http://www.oracle.com/technetwork/java/javase/downloads/index.html>), find the [Java SE 8u191/ 8u192] project and click the [JRE] download button.

Java SE 8u191 / Java SE 8u192
Java SE 8u191 / Java SE 8u192 includes important bug fixes. Oracle strongly recommends that all Java SE 8 users upgrade to this release.
[Learn more](#)

- [Installation Instructions](#)
- [Release Notes](#)
- [Oracle License](#)
- [Java SE Licensing Information User Manual](#)
 - [Includes Third Party Licenses](#)
- [Certified System Configurations](#)
- [Readme Files](#)
 - [JDK ReadMe](#)
 - [JRE ReadMe](#)

JDK
[DOWNLOAD](#)

Server JRE
[DOWNLOAD](#)

JRE
[DOWNLOAD](#)

Find the latest Java SE Runtime Environment 8u192 version, click the [Accept License Agreement] option, and then click the [Windows x64 Offline] item to download the JRE kit.

Java SE Runtime Environment 8u192

You must accept the [Oracle Binary Code License Agreement for Java SE](#) to download this software.

☐ Accept License Agreement ☒ Decline License Agreement


Product / File Description	File Size	Download
Linux x86	68.01 MB	jre-8u192-linux-i586.rpm
Linux x86	83.74 MB	jre-8u192-linux-i586.tar.gz
Linux x64	64.86 MB	jre-8u192-linux-x64.rpm
Linux x64	80.68 MB	jre-8u192-linux-x64.tar.gz
Mac OS X x64	76.15 MB	jre-8u192-macosx-x64.dmg
Mac OS X x64	67.76 MB	jre-8u192-macosx-x64.tar.gz
Solaris SPARC 64-bit	52.29 MB	jre-8u192-solaris-sparcv9.tar.gz
Solaris x64	50.16 MB	jre-8u192-solaris-x64.tar.gz
Windows x86 Online	1.8 MB	jre-8u192-windows-i586-iftw.exe
Windows x86 Offline	63.43 MB	jre-8u192-windows-i586.exe
Windows x86	66.5 MB	jre-8u192-windows-i586.tar.gz
Windows x64	71.36 MB	jre-8u192-windows-x64.exe
Windows x64	71.29 MB	jre-8u192-windows-x64.tar.gz

1.4.1 Install Essential Environment Kits

1. After installing the operating system and database software (In this manual, we take Microsoft Windows Server 2012 R2, 64bit, Microsoft SQL Server 2012 (64bit), and PostgreSQL v9.6 as example), please continue to complete the installations of Microsoft .NET Framework 4.5 or later version, and Java SE Runtime Environment v1.8 or later version.

Reminder: When installing Microsoft SQL Server, be sure you select to install the [SQL Server Management Studio] suite for creating a new database account for WorldCard Team.

2. Next, please open the web browser, enter the URL (<http://download.worldcardteam.com/>) to open the download page, select the [Windows Server Edition Download] page, and download [WorldCard Team (Server)] software, and Double-click the file to install after downloading.
3. After the installation, please do not tick to run [WorldCard Team Server Startup Settings], directly click [Finish] to complete the installation.




Chapter 2 Database Settings (MSSQL or Postgre)

2.1 Microsoft SQL Server Related Settings


2.1.1 Add Microsoft SQL Server Database Account for WorldCard Team

If you are using Microsoft SQL Server, please open [SQL Server Management Studio] first and log in to access the database with Administrator or sa with the highest permissions. Then right click on the database server and select [Properties]. On the left side of the [Security] page, make sure you have set the server authentication as [SQL Server and Windows authentication mode]; if not, please make changes and right click on the database server and choose [Restart] to restart the database server.




Next, we need to add a Microsoft SQL Server account for WorldCard Team to use, please expand the server folder, and right click on [Security] folder, then click [New \ Login]. Select [SQL Server authentication] in the [General] page, and enter the account / password you want to use (here we take “pptest” as example); Please note that the [Enforce


password policy] option below must be checked out.



Then click on the [Server Roles] on the left, and check [dbcreator] for this account, the others is not recommended to check to avoid security problems, and then click [OK] to complete.




After creating the new account, it is recommended to close the SQL Server Management Studio and re-open it again, and select [SQL Server Authentication] in the [Authentication] field of login windows, then use the account / password you just created to log in to make sure the new account can be logged in correctly.



2.1.2 Confirm Microsoft SQL Server Database connection Parameters


To connect the WorldCard Team Services to the database program, you need to create a dedicated database, and also obtain the necessary connection parameters: [SQL Server host], [SQL Server port] and [SQL Server instance name].

To confirm [SQL Server host] and [SQL Server port] information, please go to [Applications] and open [SQL Server Configuration Administrator]. Under [Server Network Configuration], select the protocol that your database uses, and then look at the [IP Addresses] page of [TCP/IP] item on the right to see the IP address and port information of the database server.



Reminder: The default setting of TCP/IP Network Protocol is enabled, if you found it is disable, please right click on it to enable, and then restart the SQL Server.

To confirm [Instance Name] information, open [SQL Server Management Studio], select [Browse] in the [Server name] field, and then expand the [Database Engine] folder, you can see the [Instance Name] right after the computer name and “/”. Please note that if you install Microsoft SQL Server without setting the Instance Name, there will be no name information here.



2.2 PostgreSQL Distributed Architecture Service Settings

If you are using PostgreSQL and PostgreSQL is not installed on the same server with WorldCard Team service, be aware that PostgreSQL needs to be set for WorldCard Team server to connect:

1. Go to C:\Program Files\PostgreSQL\9.6\data\ directory and find the [pg_hba.conf] file, and edit it by using Notepad or other software.
2. As shown below, please choose one connection parameter to add in the [IPv4 local connections] item: [host all all 10.10.12.0/24 password] or [host all all 0.0.0.0/0 trust], to enable the computers to connect to this PostgreSQL server.

The first kind of connection parameters:

- Type: host, provide connection.
- Database: all, all databases on PostgreSQL.
- User: all, all accounts on PostgreSQL.
- Address: 10.10.12.0/24, assuming WorldCard Team Server's IP section is

10.10.12.0~10.10.12.255 (the subnet mask is 255.255.255.0), 24 means the server only accept the computer in same network section to connect, which is the computer with IP 10.10.12.xx. Generally speaking, IP address split into 4 sections, the second section is 8bit, the third section is 16bit, the fourth section is 24bit, if you want to allow a computer in other network section to connect, for example, to enable a computer with IP 10.10.xx.xx to connect, you have to change 24 to 16, and also change the third IP section from 12 to 0 to make it become 10.xx.0.0.

- Method: password, use password verification.

#	TYPE	DATABASE	USER	ADDRESS	METHOD
#	IPv4	local connections:			
host	all	all	all	127.0.0.1/32	md5
host	all	all	all	10.10.12.0/24	password
#	IPv6	local connections:			
host	all	all	all	:::1/128	md5
# allow replication connections from localhost, by a user with the					
# replication privilege.					
host	replication	all	all	127.0.0.1/32	md5
host	replication	all	all	:::1/128	md5

The second kind of connection parameters:


If you think you setting IP network section is troublesome for you, you can use the second parameter.

- Type: host, provide connection.
- Database: all, all databases on PostgreSQL.
- User: all, all accounts on PostgreSQL.
- Address: 0.0.0.0/0, no IP limitation.
- Method: trust, no password verification needed.


#	TYPE	DATABASE	USER	ADDRESS	METHOD
#	IPv4	local connections:			
host	all	all	all	127.0.0.1/32	md5
host	all	all	all	0.0.0.0/0	trust
#	IPv6	local connections:			
host	all	all	all	:::1/128	md5
# allow replication connections from localhost, by a user with the					
# replication privilege.					
host	replication	all	all	127.0.0.1/32	md5
host	replication	all	all	:::1/128	md5

Chapter 3 Connect Database via WorldCard Team Startup Tool

Next, we need to connect the WorldCard Team program with database software. In [Applications] of Windows, click [WorldCard Team Startup Tool] to open.



Select whether you want to use [Quick Startup Settings] or [Advanced Startup Settings]. If you are not familiar with the server setup, and install the PostgreSQL database with WorldCard Team service on the same server, we recommend you to choose [Quick Startup Settings]; if you are using the Microsoft SQL Server database, or PostgreSQL database, but not installed on the same server with WorldCard Team Service, it is recommended to use [Advanced Startup Settings].



3.1 Quick Startup Settings

After choosing [Quick Startup Settings], it will check if the required environment kit and database software are installed and set. If there is any problem, it will be displayed as

shown in the following figure and provide your corresponding suggestions.

WorldCard Team quick startup settings

Welcome
WorldCard Team quick startup settings

Check Requirement

Configuration

Apply and Test

Start

Check Requirement

WorldCard Team system requirements check, please follow the instructions to install software and setup.

Requirement	Status
Microsoft .NET Framework	Installed(4.6 RC)
PostgreSQL	Not installed
Java SE Runtime Environment	Installed(1.8)

The necessary software has not been installed on your system, please download and install the software first.

Download PostgreSQL [Download](#)

Note :Consider the stability of the WorldCard Team system, about the third-party software install, please download and install the below recommended version.
PostgreSQL : Download PostgreSQL v9.6.

[Recheck](#) [Next](#) [Close](#)

When the check is passed, click [Next] to enter the setting procedure. In the [**Port Settings**] item, the default http and https connection ports of the WorldCard Team service are 9080 and 9443, you can use other ports instead; in the [**SQL Settings**] item, you only need to fill in the administrator password in the [Password] field that set when installing PostgreSQL. If you have modified the connection port value when installing PostgreSQL, please fill in the correct value here. In the [**Memory Configuration**] item, enter at least [4096] MB to ensure that the WorldCard Team service can work properly.

WorldCard Team quick startup settings

Welcome
WorldCard Team quick startup settings

Check Requirement

Configuration

Apply and Test

Start

Configuration

Port settings

http port:

https port:

SQL settings

Server URL: Port:

Database name:

account:

password:


Memory configuration

Memory size(MB): Max size :8192MB


[Back](#) [Next](#) [Close](#)

Chapter 3 Connect Database via WorldCard Team Startup Tool

After setting, please click [Next] to continue. At this time, WorldCard Team Server Startup Settings will check to confirm the input information is correct. If there is no error, please click [Next] to continue; if there is any error, please click [Next] to return to correct.




Click [Start] button in the [Server Status] area, then the WorldCard Team service will be initialized and run. When the status changes from red to green, you can click the [Start] button below and refer to the next chapter to register and activate your WorldCard Team server.






3.2 Advanced Startup Settings

If you choose [Advanced startup Settings], in the [JRE Settings] page, select the path of [JRE HOME], which is the JRE installation directory, for example: C:\Program Files\Java\jre1.8.xxxxx \, then click [Set] button below, there will be a check procedure, if all set, the check procedure will close up itself.



Next, in the [Server Settings] page, the default http and https ports of WorldCard Team services are 9080 and 9443, and you can change to other ports. If your company has its own SSL certificate, please assign the path to the certificate, otherwise, please use [Default Certificate]. After setting, click [Set] button below, there will be a check procedure, if all set, the check procedure will close up itself.



Chapter 3 Connect Database via WorldCard Team Startup Tool

The last page of [Database Settings] is a little complicated, and different types of database have different settings:

Microsoft SQL Server

1. Database Type: Please select the database you use, for example, MSSQL.
2. Server URL: Please fill in the [SQL Server host] information described in the previous Chapter, it is recommended that you fill in the localhost IP for now to test, then refer to Chapter 4.5 for outbound network settings.
3. Connection Parameters: If you use the default settings to install Microsoft SQL Server, please select [Default] here, if you have changed the port or Instance Name, please select [Port] or [Instance Name] and fill in the [SQL Server port] or [SQL Server Instance name] information described in the previous Chapter.
4. Database Name: Please note this cannot be changed, always named [worldcardteam].
5. Database Account / Password: This is the pptest / pptest that created in the previous Chapter, for the WorldCard Team can read and write the database correctly.

WorldCard Team Startup Settings

IRE settings Server settings Source settings

SQL settings

Library type selection
☒ MSSQL ☐ PostgreSQL

Server URL: 10.10.12.11

Server
☒ Default
☐ Port 1433
☐ Instance Name

Database name: worldcardteam

account: pptest

password: *****

Note: Please confirm login account has discriminator identity

Connection test Apply

Server status

stopped

start up stop

Database Restore Reminder

If you restore the WorldCard Team database via database management tool, to avoid the data inconsistency between client and server, please click the "Database Restore Notice" button, the client app will get the notice and then re-download data from server.

Database Restore Notice

WorldCard Team web interface


Start

1. The first time you use this product, go to the web interface and follow the steps to complete the product registration process.
2. Follow this button to enter the WorldCard Team's web interface.


v1.3.0

PostgreSQL

1. Database Type: Please select the database you use, for example, Postgre.
2. If PostgreSQL is installed locally, use the default value of [localhost], otherwise enter the PostgreSQL server's IP or URL. If PostgreSQL is not installed locally, refer to Chapter 2.2 for distributed architecture configuration.
3. Port: Please enter PostgreSQL's port, the default will be 5432.
4. Database Name: Please note that it cannot be changed, always named [worldcardteam].
5. Database Account / Password: Please enter the default administrator account (postgres) and password when installing PostgreSQL.




When all the above settings are done, click the [Set] button below and then click the [Connection Test] button to test. After passing the connection test, start the WorldCard Team service by clicking the [Start Up] button at the upper right of the [WorldCard Team Startup Tool] window, and access WorldCard Team service to activate it by clicking [Start] button at the lower right after WorldCard Team service successfully ran.



Chapter 4 Activate WorldCard Team Service

4.1 Register WorldCard Team

Following the previous chapter, when clicking [Go to the web interface], the WorldCard Team's initial registration page will open, please follow the instructions to choose for trail, or fill in the Activation Code, the Email Address of administrator, and your Company's information to activate, and **then continue to fill in the User Name and login password of Administrator.**




The registration process consists of three steps:


- Step1. Activate WorldCard Team Server.**
 - Radio button: ☒ I want to activate WorldCard Team product
 - Activation code: [] [] [] []
 - Radio button: ☐ I want to try
 - Notes:
 1. If you have already purchased WorldCard Team, please find software activation card from the retail box. Once you enter the activation code and all the registration information, you can use WorldCard Team.
 2. If you choose "I want to try", the trial period is 90 days.
 3. If you don't have the activation code of WorldCard Team, please contact us.
- Step2. Enter administrator information**
 - Admin Email: []
 - Confirm Email: []
 - Company name: []
 - Phone: []
- Step3. Set admin password**
 - User name: []
 - Password: [] (Please enter password)
 - Confirm password: [] (Please enter Password again)


4.2 Create User Accounts


Before you create any user, you have to decide to either let different users has their own permissions to share specific information, or just let all users reach all the shared information. When you create a user, you can set the user as General account or Read-Only account, and connect this user with his supervisor if there is any. After setting up, the dif-

ferent users will have different access permissions.



Please enter the first account information that is to be established, and set the level of the account, as well as the permissions and functions the account can be used; If you allow a user to export the contact data, or allow a user to help others to scan business cards (special feature on PC version), please choose the related options to enable. After finishing adding the first user, click  to add more users to complete the whole activate process.

If you want to delete the account which is created by mistake, please click  on the account picture to delete.




Note:


1. **The default password for the new user is "000000". When the user first logs in, the system will ask the user to reset the password.**
2. **All user settings can be modified in the [Manage Accounts] section of WorldCard Team settings, you may refer to Chapter 5.2.**
3. **Read-only users can add / edit their own contact data, but for [Shared Contacts] data, they can only view it, they cannot be download and edit it.**


4.3 Start to Use

WorldCard Team settings can only be changed by administrator logging in on the web page. When the activation is complete, you will see the URL of the WorldCard Team server on the screen. Click [Start] button or enter the URL in the browser to launch WorldCard Team web page.





Note: The port of the WorldCard Team service is 9080 (http) and 9443 (https). If you want to access manually or provide a URL for any user, please add [: 9080 or: 9443] after the URL to connect correctly.

After opening, please enter administrator account / password to log in. After that, we recommend you to watch the tutorial to quickly understand the functions; Then please click the  icon on the upper-right corner of screen, and choose [Settings] to enter WorldCard Team Settings.



In the settings, you can use the user account management, or adjust the data sharing settings, or add some customized fields according to the whole company's needs, if you want WorldCard Team users to connect to your company CRM system like Salesforce, please set up here.

If you want to expand the maximum number of user accounts, please click  button in the [System Overview] section to purchase more license, and then click  button to enter the activation code to update.


Please refer to the Chapter 5 for a variety of setup instructions for WorldCard Team.

4.4 Firewall Settings


Because WorldCard Team Service uses special connection ports, you have to set up the firewall to open those ports for users to connect.

The following instruction is based on the system's firewall, please set up the system firewall, router firewall and so on according to your company's equipments.


1. First of all, please open [Windows Firewall], and click [Advanced settings] on the left.




2. Click [Inbound Rules] on the left, then click [New Rules] on the right.



3. Select [Port], and select [TCP] option in the next step, then fill in the ports at [Specific local ports] that used by WorldCard Team, such as [9080, 9443].



4. Then select [Allow the connection], and tick the types of connection that to be applied to this rule in the subsequent steps, and also the name for this rule for future





5. In the last, in the [Outbound Rules] section, add the same rule to open the WorldCard Team external connections, then the whole setup is complete.

4.5 External Connection Settings

If the users need to connect back to company to use WorldCard Team Service from any external network, please refer to the following instructions to set up:

Outbound Network Uses Fixed IP

1. No matter using IP address or URL to login WorldCard Team service, please pay attention on the internal IP and external IP conversion issue. Make sure you have set the corresponding IP address of the internal WorldCard Team server on the NAT-enabled device.
2. For the URL login, the MIS engineer can set the DNS to assign a URL for WorldCard Team server, but if the DNS setting is difficult to you, you can just using IP address to login.
3. Please note the connection ports (9080 and 9443) have to be opened in all the server and internet firewalls. For the related instructions, please refer to Chapter 4.4.



External Network Uses Floating IP

1. If your company's external network IP is floating IP, we recommend you to apply for a fixed IP, or obtain a fixed URL by applying DDNS service.
2. Please note the connection ports (9080 and 9443) have to be opened in all the server and internet firewalls. For the related instructions, please refer to Chapter 4.4.


Chapter 5 WorldCard Team Settings

5.1 Basic Operations


5.1.1 Change Password / Display Name

Click  on top right corner, and then click [Profile]. Click  on each field to make changes. If you forgot the password, click [Forgot Password] on the main screen to reset.


5.1.2 Switch Interface Language

Click  on top right corner, and then click [Switch Language] to choose interface language.




5.1.3 Back to Homepage / Sign Out

Click the word [WorldCard Team] on top left corner to go back to Homepage; to sign out, click  on top right corner, and then click [Sign Out].

5.2 Admin Settings

WorldCard Team settings can only be changed by administrator logging in on the web page, and then click  on the upper-right corner of screen, and choose [Settings].

5.2.1 Manage Accounts

Here you can click the icons on the toolbar to add  or edit  user account, if any user forgot the password, please click  to reset the password back to 000000 and inform the user to log in as soon as possible to reset the password, or you can tell the user to click [Forgot Password] button on the login page by themselves to reset password.



Reminder: When creating accounts, please make sure you enter the correct Email address, to prevent users can not be logged in properly.

Add user

Account:

Email

Role:

General

Display Name:

User name

Superior:

None

Account ability:

☐ Export
☐ Scan business card for colleagues
☐ Print

Allowed platforms

Platform	Device binding
<input checked="" type="checkbox"/> IOS	<div>Off</div>
<input checked="" type="checkbox"/> ANDROID	<div>On</div>
<input checked="" type="checkbox"/> WINDOWS	<div>Off</div>
<input checked="" type="checkbox"/> MAC	<div>Off</div>
<input checked="" type="checkbox"/> WEB	

Notes:

- The default password is "000000"
- Scan business card for colleagues and print function, only supports Windows / Mac edition.
- If you want to restrict the usage of specific devices, please turn on the settings of the binding devices and check the allowed devices.
- If you need to connect to the server with public IP, please turn on the "Ignore Public IP connection setting".

OK


Cancel

If you want to restrict a user to only use Android devices or Windows computers, or even use web pages to connect, etc., please make settings in the [Allowed Platforms] project.

Tip: Each platform can be bound to up to two devices.

If you want to bind a device in advanced, for example, if the user requests that he wants to make sure his account will not be logged in by other device, you can ask the user to use the device that to be bound to connect, then you click to edit the user's account, and then click next to the platform, then the device information will list, then you can tick to bind the device.

If the user has used multiple devices to connect, in



order to ensure the correct information, as shown on the right, the user can tap on the [Device ID] of the software login screen on the device that to be bound, and provide the correct device information to the administrator via email.

Reminder:

- It is recommended to bind the device before going on a business trip. If the user is already outside of the company without binding, or his/her device is lost when he/she is outside, and need to use the new smart phone to connect. At this time, the user can use the new device to connect, although the connection will fail, the server will still have a connection record, at this point, the user can contact the administrator to bind the new device to log in again.***
- If the user leaves the company, please remember to unbind the device that has been bound to.***

If you have [Public IP Connection Restriction] enabled, it is recommended that you open the [Ignore External IP Connection Settings] if possible, because the IP address of the mobile device is usually not internal to the company. For related external IP restriction settings, please refer to the following section 5.2.8.

Device	Ignore Public IP Connection Settings
<input type="checkbox"/> ASUS_Z012DA 00000000-621c-2a50-621c-2a50621c2a50	<input type="checkbox"/>

Note:
The "Ignore Public IP Connection Settings" function can be setup, when the "Reject Public IP connection" had been turned on in security settings.

OK Cancel


5.2.2 Delete/Deactivate/Suspend User Account


If the user account is created by mistake, if this account has never logged in, you can easily click to delete it. But if this account has already logged in before, it cannot be deleted, you can only click to set this user account as inactive user. If the owner of this user account has no longer in the company, you can also set the account as inactive.

Once the user account is set as inactive, it cannot be activated again, and the contact data belongs to this user account cannot be deleted by this user account as well; If you need to transfer those contact data to new employee, please click [Inactive User] tab above, and click icon on the toolbar to inherit those contact data to the new user account (employee) who is going to take over this job, and the owner of those contact data will be changed immediately to that new employee; Or you can click to change the

data owner one by one, and the new user will be able to continue use the data.


Tips: All the shared contact data that shared by of the disabled user account can be continued use and be continuously used and updated by the users who get shared.

If the user account will be temporarily not use, click  to suspend the user account. After suspending, you can still log in to view the [My Contacts] profile, but you cannot view the [Shared Contacts] profile, and you cannot edit or share any contact data, and other users cannot share the contact data to the suspended user account.



To enable a suspended user account, click the [Pause] tab above, select the user account you want to enable, and click  to cancel the suspension.


5.2.3 Import Account from AD Server

WorldCard Team also supports the quick import of accounts from an Active Directory Server, for you to quickly create accounts.

Click  on the quick toolbar, and then enter the AD server information that to be imported (server address, server account and password, Base DN), click OK, then you can read the account information.

If you do not know the connecting information of the AD server you want to import, please refer to the Appendix of this manual.

After ticking the accounts you want to import, press the  button to add the accounts to the import list. To remove accounts from the import list, just click on the account and press  to remove it.



When the import process is complete, please edit the imported accounts to set the account's role, level and which function can be allowed, then the whole importation is done. For these imported accounts, the password to login the WorldCard Team service is the same as those settings on AD server, it will not be reset to 000000.

Reminder: The number of AD accounts that can be imported is the remaining number of accounts that you have enabled. For example, if the number of enabled accounts is 30, and 10 accounts have been manually created or imported, then the maximum number of accounts that can be imported this time is 20.

5.2.4 Sharing Rules

You already set up this during the initialization, and you can change it again here.

Standard Sharing

- Administrators can access company-wide data.
- Superior can view Subordinates' data .
- Based on sharing settings, users can view the data that shared by other users.

Company-wide Sharing


- All contacts have been shared, each account can view the company-wide contacts.

5.2.5 CRM Settings

If you want WorldCard Team users to connect to your company CRM system like Salesforce, please click [Settings] to enable.

If the administrator enables the feature to connect CRM system, click CRM Settings under General Settings, and input log in information of your CRM system. You can manually export contacts to CRM systems, or have WorldCard Team synced with CRM. WorldCard Team will sync with CRM system every 10 minutes if the sync function is on.

5.2.6 Custom Field

WorldCard Team provides field customization feature, you can add up to 16 customized fields. Please click  to add new field. and then enter the field title and field property to complete.





There are 7 properties for custom fields:

1. Text: Can fill in texts and symbols.
2. URL: Can enter URL information.
3. Email: Can only fill in the data with Email format.
4. Picklist: Customize menu content to allow users to select, the menu item limitation are 10.
5. Number: You can only enter integer numbers.
6. Floating-point Number: You can enter a value that contains a decimal point.
7. Date: Add date.
8. Date Time: Add date and time.

Reminder: *In the contact edit screen, if the input box frame is displayed in red, it means that the input data format is not accepted, please check and correct.*

5.2.7 System Overview

Here you will see information about the current usage of the WorldCard Team server, including how many users and how many contacts, and more. To add more user licenses, please click  to purchase, and then click  to activate.


Reminder: *If your administrator account is imported from the AD server, and the AD account does not have Email information, WorldCard Team will remind you to add Email information in [Personal Information] in order to increase the authorization when adding authorization.*

5.2.8 Certificate Information

This page displays the https certificate information of the https protocol that WorldCard Team server uses. If you want to use your company's own https certificate, please open [WorldCard Team Startup Tool] to change, you need to reboot the WorldCard Team server to take effect.


If you do not have a formal https certificate, you will see warnings about non-secure websites when you access your WorldCard Team webpage with your browser. You may choose to continue using (depending on the browser type, there will be different ways to allow continued use) or replace with your company's certification, then there will be no more warning message.

5.2.9 Security Settings

Enable this feature when you want to restrict users to access to the WorldCard Team server only from company's internal IP or a device with a specific external IP address. For example, if you only allow a Windows computer in the boss's home to connect, or only the branch office staffs can connect, you can click  to fill in the range of IP addresses or an IP segment that can be allowed to connect. .

5.3 General Settings

5.3.1 Share Settings

Here you can choose whether you want to automatically share the new added contacts with the specific users or not. When Share Settings function is turned on, newly added contacts will be shared with the specified users, and the user you shared to will receive the notifications. Click  to remove users from the sharing list.

For Notification information, please refer to Chapter 5.4; for detailed information regarding Share Settings, please refer to Chapter 2.2.4 of [Web User Manual].

In addition, you can click the [Clear the contacts never being downloaded by any user] button to delete the contacts that belong to you but never downloaded by anyone, and this can let you save more useful information.

5.3.2 Display Settings

Under [Display Map of Address], you can choose an online map to display the address of contacts.

- **Auto:** System selects map basing on contact country information. Baidu map for China; Google map for other countries.
- **Google Map:** To display address on Google Map
- **Baidu Map:** To display address on Baidu Map.


Under [Display Name Settings], you can decide the display order of first Name and last Name. Eastern names and western names can have different settings.




5.3.3 CRM Settings

WorldCard Team can work with CRM systems. If the administrator enable the feature to connect CRM system, click CRM Settings under General Settings, and input log in information of your CRM system. You can either manually export contacts to CRM systems, or have WorldCard Team synced with CRM. WorldCard Team will sync with CRM system every 10 minutes if the sync function is on.

5.4 Notification

You will receive notification when someone shares a contact with you, or WorldCard Team settings have been updated. Click  on the top right corner of the main screen to review messages.

Messages from the system or other users can't be deleted manually. The system has a limit of 500 messages to display. Once it reaches the limit, the oldest messages will be automatically deleted by the system.

If you are notified that someone shared a contact with you, you will see the key information of the contact in the notification, including name and company. You can select the contact and click  to download the contact to [My Contacts].

Note: You can click *Date / Sharer / Description* on top of the screen to sort your notification messages.


Chapter 6 WorldCard Team Applications Installation

© Windows

To install WorldCard Team application, please open web browser and access (<http://download.worldcardteam.com/>) to open download page, then click [WorldCard Team (Windows)] to download. When the download is finished, please double click it to start install.

After installing and launching the WorldCard Team application, please enter the WorldCard Team server URL and key in your account / password to log in.

© Mac

To install WorldCard Team application, please open App Store  in Mac system, and enter [WorldCard Team] in the upper-right search bar to search.

Click [Get] button, and enter your Apple account / password to start download. When the download is finished, you will be able to find WorldCard Team application in [Applications].

After launching the WorldCard Team application, please enter the WorldCard Team server URL and key in your account / password to log in.

© iOS / Android

To install WorldCard Team app, please open App Store / Google Play in your iOS / Android device, and search [WorldCard Team] to download and install.

Or you can read the QR code below to access the download page:

iOS



Android



After downloading and launching the WorldCard Team app, please enter the WorldCard Team server URL and your account / password to log in.


** Reminder: You are advised to log out WorldCard Team to reduce server's loading if you are not accessing it.*

Chapter 7 Database Backup / Restore


7.1 Back up Microsoft SQL Server Database

To back up WorldCard Team's database of Microsoft SQL Server, please follow these steps:


1. Please open [WorldCard Team Server Startup Settings] and stop the WorldCard Team service.
2. Click [SQL Server Management Studio] in [Applications] to open the console and login with Administrator or sa account.




3. Expand [Databases] in the left pane and locate WorldCard Team's database [worldcardteam]. Right-click on it and select [Tasks \ Back Up].



4. After confirming the path to save the backup file, click the [OK] button to start the backup.



- After the backup is complete, you can see the file appears in the destination folder your assigned.




Reminder: The business card images will be backed up together with the database, and will be restored together.

7.2 Restore Microsoft SQL Server Database


To restore WorldCard Team's database of Microsoft SQL Server, please follow these steps:

- Click [SQL Server Management Studio] in [Applications] to open the console and login with Administrator or sa account.
- Expand [Databases] in the left pane and locate WorldCard Team's database [worldcardteam]. Right-click on it and select [Delete] to delete the current database


that you don't want to use anymore; If you are willing to restore on the new server, please skip this step.




3. Right-click on [Database] in the left pane and select [Tasks \ Restore \ Database].



4. Select [Device] in [Source] section, and browse the database backup file in this computer, and click [OK] to restore.



5. After the database is restored, please open [WorldCard Team Server Startup Settings], and after the WorldCard Team service is running, click the [Database Restore Notification] button at the bottom right. At this time, the WorldCard Team server will notify all client software that the database has been restored and needs to compare and update to the restored data on the server.




7.3 Back up PostgreSQL Database

To back up WorldCard Team's database of PostgreSQL, please follow these steps:


1. Please open [WorldCard Team Server Startup Settings] and stop the WorldCard

Team service.


2. Go to the PostgreSQL console by clicking [pgAdmin4] from [Applications].




3. Expand [Server \ PostgreSQL 10 \ Databases] in the left pane and locate WorldCard Team's database [worldcardteam]. Right-click and it select [Backup].





4. Enter the backup database file name for future to identify, and click the [Backup] button, it will start the backup.



5. After the backup is complete, the backed up database file will be stored in the [Documents], if you want to check the correct path, you can click [Click here for details] wording on the pop-up message.






Reminder: The business card images will be backed up together with the database, and will be restored together.


7.4 Restore PostgreSQL Database

To restore WorldCard Team's database of PostgreSQL, please follow these steps:


1. Go to the PostgreSQL console by clicking [pgAdmin4] from [Applications].
2. Expand [Server \ PostgreSQL 10 \ Databases] in the left pane and locate WorldCard Team's database [worldcardteam]. Right-click and it select [Delete] to delete the current database that you don't want to use anymore; If you are willing to retore on the new server, please skip this step.




3. Right-click on [Datebases] in the left pane, select [Create \ Database], and set the new database name to the same [worldcardteam].



- Once created, right-click on the new worldcardteam database and select [Restore], then select the previously backed up database file to restore.



- After the database is restored, please open [WorldCard Team Server Startup Settings], and after the WorldCard Team service is running, click the [Database Restore Notification] button at the bottom right. At this time, the WorldCard Team server will notify all client software that the database has been restored and needs to compare and update to the restored data on the server.




Appendix A: Connecting Information of AD Server


If you are not clear with the connecting information of AD server, please refer to the instructions below:

1. Access the URL below to download and install the free AD Explorer tool of Microsoft: <https://technet.microsoft.com/en-us/sysinternals/bb963907.aspx>
2. Execute "ADExplorer.exe", and Click [File] \ [Connect], and enter the IP address/ Account/password of your company's to connect.

Reminder: This IP address/Account/Password are the required information to fill in when you import the AD accounts to WorldCard Team. Please note the account must be an domain admin account.




3. Then in the left pane, expand the user directory under the server. As shown in the following image, find the [DistinguishedName] item in the user directory. The value of this item is [BaseDN], which is the information to be filled in WorldCard Team software. As a result, all accounts in this user's directory will be imported.



Appendix B: AN240W Duplex Scanner Instructions (Optional)

B.1 Hardware Function Introduction



B.2 Installation and Setup


Please connect the scanner power first. To use the cable network, please connect the network cable; to use the wireless network, please refer to the subsequent wireless network settings.

Note: *The network that the scanner connected must be in the same local network as the WorldCard Team server.*

Please press the scanner's power button to turn it on, when the operation screen appears, it means you can start to use it. Please tap [Settings] on the left menu, then tap [Network]. Here you will see the switch between the wireless network and the cable network. Please choose one of them to continue.



To use the wireless network, tap on the wireless item to enter the connection screen, then you can select the wireless network name you want to connect.




B.3 Start Scanning Business Cards

Please tap [plug-in] on the left menu and select [WorldCard Team] to open World-Card Team program.




Please enter the IP address of the WorldCard Team server in the start screen, click Next, then click [Add User] to log in to your personal WorldCard Team account.






After logging in, please choose the business card language to be recognized, and the user you want to scan to (the default user you scan to is yourself), then you can put the business card horizontally into the business card feed, and tap the [Scan] to scan.



Tips:

- 1. The flaps on both sides of the card placement can be slid and adjusted to an appropriate size, and you can do the batch scanning at one time (up to 80 sheets).***
- 2. The scanner is a double-sided scanning model, so there is no need to concern placing a business card with front or back side face up.***

After scanning, the actions of recognition and uploading to the WorldCard Team server will be performed, and the whole scanning process will be finished after the upload is completed.



* For scanning regular papers, please refer to the disc documentation included in the scanner package.

WorldCard Team - Windows Server Edition

v1.5 Administrator Manual

Manufacturer: PenPower Technology Ltd.

Release: June, 2019